



Category:

- [-] Session
 - Logging
- [-] Terminal
 - Keyboard
 - Bell
 - Features
- [-] Window
 - Appearance
 - Behaviour
 - Translation
 - [+] Selection
 - Colours
- [-] Connection
 - Data
 - Proxy
 - [+] SSH
 - Serial
 - Telnet
 - Rlogin
 - SUPDUP

Basic options for your PuTTY session

Specify the destination you want to connect to

Host Name (or IP address)

127.0.0.1

Port

2023

Connection type:

☐ SSH☐ Serial☒ Other:

Raw



Load, save or delete a stored session

Saved Sessions

openvms

Default Settings

COM3

allstar

openvms

Load

Save

Delete

Close window on exit:

☐ Always☐ Never☒ Only on clean exit

About

Help

Open

Cancel



Category:

- Session
 - Logging
 - Terminal**
 - Keyboard
 - Bell
 - Features
- Window
 - Appearance
 - Behaviour
 - Translation
 - Selection
 - Colours
- Connection

Options controlling the terminal emulation

Set various terminal options

- ☒ Auto wrap mode initially on
- ☐ DEC Origin Mode initially on
- ☐ Implicit CR in every LF
- ☐ Implicit LF in every CR
- ☒ Use background colour to erase screen
- ☐ Enable blinking text

Answerback to ^E:

PuTTY

Line discipline options

Local echo:

- ☐ Auto
- ☐ Force on
- ☒ Force off

Local line editing:

- ☐ Auto
- ☐ Force on
- ☒ Force off

Remote-controlled printing

Printer to send ANSI printer output to:

Apply

Cancel



Category:

- Session
 - Logging
- Terminal
 - Keyboard
 - Bell
 - Features
- Window**
 - Appearance
 - Behaviour
 - Translation
 - + Selection
 - Colours
- Connection
 - Data
 - Proxy
 - + SSH
 - Serial
 - Telnet
 - Rlogin
 - SUPDUP

Options controlling PuTTY's window

Set the size of the window

Columns

Rows

80

24

When window is resized:

- ☒ Change the number of rows and columns
- ☐ Change the size of the font
- ☐ Change font size only when maximised
- ☐ Forbid resizing completely

Control the scrollbar in the window

Lines of scrollbar

2000

- ☒ Display scrollbar
- ☐ Display scrollbar in full screen mode
- ☐ Reset scrollbar on keypress
- ☒ Reset scrollbar on display activity
- ☒ Push erased text into scrollbar

About

Help

Open

Cancel



Category:

- [-] Session
 - Logging
- [-] Terminal
 - Keyboard
 - Bell
 - Features
- [-] Window
 - Appearance
 - Behaviour**
 - Translation
 - [+] Selection
 - Colours
- Connection

Configure the behaviour of PuTTY's window

Adjust the behaviour of the window title

Window title:

openvms

☐ Separate window and icon titles☒ Warn before closing window☒ Window closes on ALT-F4☐ System menu appears on ALT-Space☐ System menu appears on ALT alone☐ Ensure window is always on top☐ Full screen on Alt-Enter

Apply

Cancel



Category:

- Session
 - Logging
- Terminal
 - Keyboard
 - Bell
 - Features
- Window
 - Appearance
 - Behaviour
 - Translation
 - Selection
 - Colours
- Connection

Options controlling character set translation

Character set translation

Remote character set:

DEC-MCS

(Codepages supported by Windows but not listed here, such as CP866 on many systems, can be entered manually)

- ☐ Treat CJK ambiguous characters as wide
- ☐ Caps Lock acts as Cyrillic switch

Adjust how PuTTY handles line drawing characters

Handling of line drawing characters:

- ☒ Use Unicode line drawing code points
- ☐ Poor man's line drawing (+, - and |)
- ☐ Font has XWindows encoding
- ☐ Use font in both ANSI and OEM modes
- ☐ Use font in OEM mode only
- ☐ Copy and paste line drawing characters as lqqqk
- ☐ Enable VT100 line drawing even in UTF-8 mode

Apply

Cancel



Category:

- [-] Session
 - Logging
- [-] Terminal
 - Keyboard
 - Bell
 - Features
- [-] Window
 - Appearance
 - Behaviour
 - Translation
 - [+] Selection
 - Colours
- [-] Connection
 - Data
 - Proxy
 - [+] SSH
 - Serial
 - Telnet
 - Rlogin
 - SUPDUP

Options controlling Telnet connections

Telnet protocol adjustments

Handling of OLD_ENVIRON ambiguity:

☒ BSD (commonplace) ☐ RFC 1408 (unusual)

Telnet negotiation mode:

☒ Passive ☐ Active☐ Keyboard sends Telnet special commands☐ Return key sends Telnet New Line instead of ^M

About

Help

Open

Cancel